
Masters in FINANCE

VALUATION WITH CORPORATE TAXES WACC, APV, FTE METHODS

Corporate Investment Appraisal

Fall 2014





OUTLINE



We consider the following **assumptions** to start with, and introduce the three methods:

- 1. The project has average risk (same risk as the firm);
- 2. The firm's D/E ratio is constant (r_E and r_W acc will be constant);
- 3. Corporate Taxes are the only imperfection.

WACC: Weighted Average Cost of Capital;

APV: Adjusted Present Value;

FTE: Flow to Equity.

We them consider alternative Leverage Policies, for which the APV method is more convenient to use:

Constant Interest Coverage Ratio;

Predetermined Debt Levels.

Other special cases later.

Constant D/E ratio:WACC Method



Remember what the weighted average cost of capital

is:

$$r_{wacc} = \frac{E}{E + D} r_E + \frac{D}{E + D} r_D (1 - \tau_c)$$

An investment's initial levered value is given by the present value of the FCFs discounted at the rate rwacc:

$$V_0^L = \frac{FCF_1}{1 + r_{wacc}} + \frac{FCF_2}{(1 + r_{wacc})^2} + \frac{FCF_3}{(1 + r_{wacc})^3} + \cdots$$

Constant D/E ratio: WACC Method





Example: Avco, Inc. Is a manufacturer of custom packaging products, and is considering introducing a new line of packaging (the RFX series). The spreadsheet forecasts the project's expected FCFs:

		Year	0	1	2	3	4
Incr	emental Earnings Forecast (\$ million	n)					
1	Sales		_	60.00	60.00	60.00	60.00
2	Cost of Goods Sold		_	(25.00)	(25.00)	(25.00)	(25.00)
3	Gross Profit		_	35.00	35.00	35.00	35.00
4	Operating Expenses		(6.67)	(9.00)	(9.00)	(9.00)	(9.00)
5	Depreciation		_	(6.00)	(6.00)	(6.00)	(6.00)
6	EBIT		(6.67)	20.00	20.00	20.00	20.00
7	Income Tax at 40%		2.67	(8.00)	(8.00)	(8.00)	(8.00)
8	Unlevered Net Income		(4.00)	12.00	12.00	12.00	12.00
Free	e Cash Flow						
9	Plus: Depreciation		_	6.00	6.00	6.00	6.00
10	Less: Capital Expenditures		(24.00)	_	_	_	-
11	Less: Increases in NWC		_	_	_	_	
12	Free Cash Flow		(28.00)	18.00	18.00	18.00	18.00

Constant D/E ratio: WACC Method



To determine the firm's rwacc we need the market values (when possible) of Equity and of net Debt, as well as the cost of equity (rE), the cost of debt (rD) and the corporate tax rate (Tc):

Assets		Liabilitie	s	Cost	of Capital
Cash	20	Debt	320	Debt	6%
Existing Assets	600	Equity	300	Equity	10%
		Total Liabilities and Equity	620		

$$r_{wacc} = \frac{E}{E + D} r_E + \frac{D}{E + D} r_D (1 - \tau_c) = \frac{300}{600} (10\%) + \frac{300}{600} (6\%) (1 - 0.40)$$

$$= 6.8\%$$

Note that net debt D=320-20; and that D/(D+E)=0.5, or D/E=1.

Constant D/E ratio: WACC Method



- •The value of the project, including the tax shield from debt, is calculated as the present value of its future free cash flows.
- •We are assuming that the project uses the same capital structure, target D/E=1.

$$V_0^L = \frac{18}{1.068} + \frac{18}{1.068^2} + \frac{18}{1.068^3} + \frac{18}{1.068^4} = \$61.25 \text{ million}$$

The NPV of the project is \$33.25 million

\$61.25 million – \$28 million = \$33.25 million

Constant D/E ratio: WACC Method Summary



- 1. Determine the free cash flow of the investment.
- 2. Compute the weighted average cost of capital.
- 3. Compute the value of the investment, including the tax benefit of leverage, by discounting the free cash flow of the investment using the WACC.

Implementing the constant D/E ratio



- In the example just seen we considered a constant ratio D/E=1 or D/(D +E)=0.5.
- By this we mean that every year the value of Debt is 50% of the (present) value of the project. Debt Capacity is a fixed proportion of VL.
- So we know that in the beginning (time 0) the new debt that the firm must raise for the RFX project is:

$$D_0 = 0.5 \times \$61.25 = 30.62$$

Constant D/E ratio: Implementing the constant D/E ratio





For each year, as time passes, we can recompute V_t^L and D_t .

		Year	0	1	2	3	4
Proj	ect Debt Capacity (\$ million)						
1	Free Cash Flow		(28.00)	18.00	18.00	18.00	18.00
2	Levered Value, V^L (at $r_{wacc} = 6.8\%$)		61.25	47.41	32.63	16.85	_
3	Debt Capacity (at d = 50%)		30.62	<u>23.71</u>	16.32	8.43	_

For example, after the first year passes:

$$V_1^L = \frac{18}{(1+0.068)} + \frac{18}{(1+0.068)^2} + \frac{18}{(1+0.068)^3} = 47.41$$
$$D_1 = 0.5 \times 47.41 = 23.71$$

2. Constant D/E ratio:

APV Method



The Adjusted Present Value (APV) method is an alternative to the WACC method.

If first values the project as if it were unlevered:

And separately adds the present value of the interest tax shield.

$$V^{L} = V^{U} + PV$$
(Interest Tax Shield)

Constant D/E ratio: APV Method



In the first step, the APV method determines the unlevered value of the firm, by discounting the FCFs at the unlevered cost

of capital ru or Pre-Tax WACC.

$$r_U = \frac{E}{E + D} r_E + \frac{D}{E + D} r_D = \text{Pretax WACC}$$

In Avco's RFX project Example:

$$r_U = 0.50 \times 10.0\% + 0.50 \times 6.0\% = 8.0\%$$

$$V^U = \frac{18}{1.08} + \frac{18}{1.08^2} + \frac{18}{1.08^3} + \frac{18}{1.08^4} = $59.62 \text{ million}$$

Constant D/E ratio:

APV Method



In the second step of the APV method we compute the present value of the interest tax shield.

Note this is easy (possible!) after knowing the Debt Capacity in each year...*

From the Debt Capacity we estimate the annual interest payments:

Interest paid in year
$$t = r_D \times D_{t-1}$$

• The interest tax shield is equal to the interest paid multiplied by the corporate tax rate.

Note: With a target D/E ratio the WACC method is more convenient.

* Note:

If you don't know the Debt Capacity per period (and interest payments per period) perhaps you can solve iteratively in excel.

Constant D/E ratio: APV Method



We compute the **Annual Interest Tax Shields**:

		Year	0	1	2	3	4
Interes	st Tax Shield (\$ million)						
1 D	ebt Capacity, <i>D_t</i>		30.62	23.71	16.32	8.43	_
2 Ir	nterest Paid (at $r_D = 6\%$)			1.84	1.42	0.98	0.51
3 Ir	nterest Tax Shield (at $\tau_c = 40\%$)			0.73	0.57	0.39	0.20

And the present value of the interest tax shields, by discounting them at the unlevered cost of capital **Y**U (or Pre-Tax WACC).

$$PV$$
(interest tax shield) = $\frac{0.73}{1.08} + \frac{0.57}{1.08^2} + \frac{0.39}{1.08^3} + \frac{0.20}{1.08^4} = 1.63 million

Note: When the firm maintains a **target leverage ratio**, its future **interest tax shields** have similar risk to the project's cash flows, so they should be **discounted at the project's unlevered cost of capital**.

Constant D/E ratio: APV Method



Finally we get the same Levered Value for the project, as with the WACC method:

$$V^{L} = V^{U} + PV$$
(interest tax shield) = 59.62 + 1.63 = \$61.25 million

The difficulty with applying the APV method is when the debt capacity is not known, but just the target D/E ratio. In that case you would need to determine simultaneously V_t^L and D_t .

Constant D/E ratio: APV Method Summary



- Determine the investment's value without leverage.
- 2. Determine the present value of the interest tax shield.
 - a. Determine the expected interest tax shield.
 - b. Discount the interest tax shield.
- 3. Add the unlevered value to the present value of the interest tax shield to determine the value of the investment with leverage.

3. Constant D/E ratio: FTE Method



The Flow-to-Equity method is:

A valuation method that calculates the free cash flow available to equity holders, FCFE, taking into account all payments to and from debt holders

The cash flows to equity holders are then discounted using the equity cost of capital r_E .

Gives you the value of Equity – same as V_L-D.

Constant D/E ratio: FTE Method



The method starts by calculating the FCFE, which can be obtained by adjusting the FCF:

$$FCFE_t = FCF_t - (1 - \tau_C) \times InterestPayments_t + Net Borrowing_t$$
or
 $FCFE_t = Net Income_t + Depreciation_t - Capital Expenditures_t - Increases in NWC_t$
 $+ Net Borrowing_t$

The Net Borrowing of a certain year is the change in the level of debt from the previous year:

Net Borrowing at Date
$$t = D_t - D_{t-1}$$





In the Avco Example, compute the FCFE:

C	omputing	FCFE	from FC	F for Avo	o's RF	X Project	:
		Year	0	1	2	3	4
Free Cash Flow to Equity (\$ m		(28.00)	18.00	18.00	18.00	18.00	
3 Net Borrowing			20.62 -	(1.10) (6.92)	(0.05) (7.30)	(0.59) (7.89)	(8.43)
4 Free Cash Flow to Equity			2.62	9.98	9.76	9.52	9.27
Year	0		1	2		3	4
EBIT	-6,67	2	0,00	20,00	2	0,00	20,00
Interest Expenses	0	:	1,84	1,42	(),98	0,51
PreTax Income	-6,67	1	8,16	18,58	1	9,02	19,49
Income Tax (40%)	-2,67	-	7,26	7,43	-	7,61	7,80
Net Income	-4,00	1	0,90	11,15	1	1,41	11,70
+ Depreciation	0,00	(5,00	6,00	(5,00	6,00
- Capital Expenditures	-24,00) (0,00	0,00	(0,00	0,00
- Increases in NWC	0,00	(0,00	0,00	(0,00	0,00
+ Net Borrowing	30,62		6,92	-7,39	_	7,89	-8,43
Free Cash Flow to Fauity	2.62		9.98	9.76		9.52	9.27

Clara Raposo

Constant D/E ratio: FTE Method



Because the FCFE is for equity-holders only, we compute the net present value of the Equity invested in the project as the present value of the FCFEs,

discounted at the equity cost of capital, re.

$$NPV(FCFE) = 2.62 + \frac{9.98}{1.10} + \frac{9.76}{1.10^2} + \frac{9.52}{1.10^3} + \frac{9.27}{1.10^4} = $33.25 \text{ million}$$

This is the same NPV we saw with the WACC method and with the APV method.

Note: The FTE method is only easy to apply when we know the interest payments each year.

Constant D/E ratio: FTE Method Summary



- Determine the free cash flow to equity of the investment.
- 2. Determine the equity cost of capital.
- 3. Compute the equity value by discounting the free cash flow to equity using the equity cost of capital.

4. Project-Based Cost of Capital



It is quite possible that firms use a different capital structure when financing a new project, or that a new project is not in the same line of business.

In this case the "old" discount rates of the firm should not be used for the project.

How to calculate the cost of capital for the project's cash flows when a project's risk and leverage differ from the firm's?

Project-Based Cost of Capital: (i) Estimating the Unlevered Cost of Capital



Example: Suppose Avco launches a new plastics manufacturing division.

We can estimate **Y**U for the plastics division by looking at other single-division plastics firms that have similar business risks (Comparables).

Firm	Equity Cost of Capital	Debt Cost of Capital	Debt-to-Value Ratio, $D/(E+D)$
Comparable #1	12.0%	6.0%	40%
Comparable #2	10.7%	5.5%	25%

For each competitor we get:

Competitor 1:
$$r_U = 0.60 \times 12.0\% + 0.40 \times 6.0\% = 9.6\%$$

Competitor 2:
$$r_U = 0.75 \times 10.7\% + 0.25 \times 5.5\% = 9.4\%$$

For the average project in the plastics industry:

$$r_U = 9.5\%$$

Project-Based Cost of Capital: (i) Estimating the Unlevered Cost of Capital



Knowing **I**U allows us to use the APV method.

To use the WACC or the FTE methods, we need to assess the cost of equity refer the project.

With a target D/E ratio we use MMII:

$$r_E = r_U + \frac{D}{E}(r_U - r_D)$$

In the Avco plastics division Example (D/E=1, Γ U=9.5%, and Γ D=6% for Avco):

$$r_E = 9.5\% + \frac{0.50}{0.50}(9.5\% - 6\%) = 13.0\%$$

Project-Based Cost of Capital: (ii) Project Leverage and the WACC



The weighted average cost of capital for the project in the plastics division would be:

$$r_{WACC} = 0.50 \times 13.0\% + 0.50 \times 6.0\% \times (1 - 0.40) = 8.3\%$$

If the target D/E ratio were different for this project, we would use the

unlevered rate Γ_U =9.5% of the project's industry, and compute Γ_E and Γ_{Wacc} based on the new D/E ratio.

Suppose
$$\frac{D}{E} = 0.75$$

 $r_E = 9.5\% + 0.75(9.5\% - 6\%) = 12.125\%$
 $r_{wacc} = \frac{1}{1 + 0.75}12.125\% + \frac{0.75}{1 + 0.75}6\%(1 - 40\%) = 8.47\%$

Project-Based Cost of Capital: (ii) Project Leverage and the WACC



Indeed, knowing a project's (industry's) unlevered cost of capital, is crucial to determine the WACC rate under different target leverage ratios.

An alternative way of re-estimating rate WACC when target ratio D/E changes is:

$$r_{wacc} = r_U - \frac{D}{E + D} \tau_c r_D$$

In the last example of slide 24 we can confirm:

$$r_{wacc} = 9.5\% - \frac{0.75}{1 + 0.75} 40\% \times 6\% = 8.47\%$$

5. APV Method with Other Leverage Policies



Besides the policy of keeping a target ratio D/E, there are other common leverage policies.

We will have a look at 2 cases, which are well captured by the APV method:

Constant Interest Coverage Ratio; Predetermined Debt Levels.

5.1. APV Method: Constant Interest Coverage Ratio **ECONO**





When a firm keeps its interest payments equal to a target fraction of its free cash flows we say it has a constant interest coverage ratio.

If the target fraction is *k*, then:

Interest Paid in Year
$$t = k \times FCF_t$$

To implement the APV approach, the present value of the tax shield under this policy needs to be computed:

$$PV(\text{Interest Tax Shield}) = PV(\tau_c k \times FCF) = \tau_c k \times PV(FCF)$$

= $\tau_c k \times V^U$

With a constant interest coverage policy, the value of the interest tax shield is proportional to the project's unlevered value.

APV Method: Constant Interest Rate Coverage ECONO





The value of the levered project, using the APV method, is:

Levered Value with a Constant Interest Coverage Ratio

$$V^{L} = V^{U} + PV \text{(interest tax shield)} = V^{U} + \tau_{c}k \times V^{U}$$
$$= (1 + \tau_{c}k)V^{U}$$

Example: In the Avco RFX project, if the firm plans to use debt such that interest is always 20% of the FCF, the value of the levered project is:

$$V^{L} = (1 + 0.4 \times 20\%)\$59.62 = \$64.39$$
 million

5.2. APV Method: Predetermined Debt Levels Econo





A firm may adjust its debt according to a fixed schedule that is known in advance.

Example: For the RFX project, assume now that Avco plans to borrow \$30.62 million and then will reduce the debt on a fixed schedule:

		Year	0	1	2	3	4
Inte	rest Tax Shield (\$ million)						
1	Debt Capacity, D _t		30.62	20.00	10.00	_	—
2	Interest Paid (at $r_D = 6\%$)			1.84	1.20	0.60	—
3	Interest Tax Shield (at $\tau_c = 40\%$)			0.73	0.48	0.24	

When debt levels are set according to a fixed schedule, we can discount the predetermined interest tax shields using the debt cost of capital.

$$PV$$
(interest tax shield) = $\frac{0.73}{1.06} + \frac{0.48}{1.06^2} + \frac{0.24}{1.06^3} = 1.32 million

APV Method: Predetermined Debt Levels **Economics** &





If debt had a constant predetermined level D forever, we would actually get:

$$V^L = V^U + \tau_C D$$